

ZipaBox

- ▶ On the Z-Wave device click the 'Settings' (top-right of device box)
- ▶ Go to the Bindings tab
- ▶ Choose the device you wish to associate it with
- ▶ Click the 'Save' button and close the Devices List menu
- ▶ Click 'Synchronise' in the main dashboard

Edit endpoint information

General	Bindings
<input type="checkbox"/> On/Off boiler actuator	
<input type="checkbox"/> Relay FGS221 - Ch1	
<input type="checkbox"/> Relay FGS221 - Ch2	
<input checked="" type="checkbox"/> Siren	

Related Information

- ▶ Multi-channel Association
- ▶ APNT-1: Installing a Fibaro Dimmer module in a Wall Switch
- ▶ APNT-2: 2-way Lighting Using Fibaro Dimmer Modules
- ▶ APNT-3: Configuring Fibaro modules in the VERA controller